Basic tests using abm_regular() and abm_variable()

Sasha D. Hafner

28 May, 2025 14:43

Overview

Objective is to demonstrate flexibility in substrate definitions. Particulate substrates can be entered through sub_pars in any number now.

Prep

```
devtools::load_all()
```


i Loading ABM

Parameters


```
grp_pars <- list(grps = c('m0', 'm1', 'm2', 'sr1'),</pre>
                  yield = c(default = 0.05, sr1 = 0.065),
                  xa_fresh = c(m0 = 0.0628, m1 = 0.0628, m2 = 0.0628, sr1 = 0.0628),
                  xa_{init} = c(all = 0.0628),
                  dd_rate = c(all = 0.02),
                  ks = c(default = 1.153337, sr1 = 0.461335),
                  qhat_opt = c(m0 = 1, m1 = 1, m2 = 2, sr1 = 8.95),
                  T_{opt} = c(m0 = 18, m1 = 18, m2 = 28, sr1 = 43.75),
                  T_{min} = c(m0 = 0, m1 = 6.41, m2 = 6.41, sr1 = 0),
                  T_{max} = c(m0 = 25, m1 = 25, m2 = 38, sr1 = 51.25))
mic_pars <- list(ks_S04 = 0.00694,
                 km_urea = 0.913
sub_pars <- list(subs = c('VSd'),</pre>
                  T_{opt_hyd} = c(VSd = 60),
                  T_{\min} = c(all = 0),
                  T_{max_hyd} = c(all = 90),
                 hydrol_opt = c(VSd = 0.1),
                  sub_fresh = c(VSd = 50),
                  sub_init = c(VSd = 30))
man_pars <- list(conc_fresh = c(VFA = 2),</pre>
                   pH = 7, dens = 1000)
```

0. Single substrate


```
out0 \leftarrow abm(365,
              grp_pars = grp_pars,
             man_pars = man_pars,
             mic_pars = mic_pars,
              sub_pars = sub_pars)
##
       VSd
## 333.15
plot(CH4_emis_rate ~ time, data = out0, type = '1')
      00009
      40000
CH4_emis_rate
      20000
      0
              0
                                  100
                                                      200
                                                                           300
                                                  time
plot(CH4_emis_cum ~ time, data = out0, type = '1')
```









plot(VSd ~ time, data = out0, type = '1')




plot(VFA ~ time, data = out0, type = 'l')



plot(VSd_conc ~ time, data = out0, type = '1')









1. Two substrates through sub_pars


Add pr for protein.

```
sub_fresh = c(VSd = 50),
                  sub_init = c(VSd = 30))
out1 \leftarrow abm(365,
             grp_pars = grp_pars,
             man_pars = man_pars,
             mic_pars = mic_pars,
             sub_pars = sub_pars)
## Error in expandPars(pars = pars, elnms = pars$subs, parnms = sub_par_nms): Size-variable parameter p
Add missing elements.
sub_pars <- list(subs = c('VSd', 'pr'),</pre>
                  T_{opt}hyd = c(VSd = 60, pr = 50),
                  T_{\min} = c(all = 0),
                  T_{max_hyd} = c(all = 90),
                  hydrol_opt = c(VSd = 0.1, pr = 0.04),
                  sub_fresh = c(VSd = 50, pr = 50),
                  sub_init = c(VSd = 30, pr = 0))
out1 \leftarrow abm(365,
             grp_pars = grp_pars,
             man_pars = man_pars,
             mic_pars = mic_pars,
             sub_pars = sub_pars)
##
      VSd
               pr
## 333.15 323.15
plot(CH4_emis_rate ~ time, data = out1, type = 'l')
      8e+04
CH4_emis_rate
      4e+04
                                100
             0
                                                    200
                                                                        300
                                                time
```


plot(CH4_emis_cum ~ time, data = out1, type = 'l')








plot(VSd_conc ~ time, data = out1, type = 'l')



plot(pr_conc ~ time, data = out1, type = 'l')



plot(VFA_conc ~ time, data = out1, type = '1')

